Roland



TR-1000 APP

Owner's Manual

About the TR-1000 APP

The TR-1000 APP is an app that lets you edit the kits of the TR-1000. To use the TR-1000 APP, you must connect it to the TR-1000.



Updating the TR-1000

If you see the following message when you launch the app, download the latest version of the app or update the firmware.



Updating the app to the latest version

Launch Roland Cloud Manager, and install the latest version of the TR-1000 APP.

Updating the firmware to the latest version

Back up or export your data from the menu on the unit.


- * For details, refer to "Backing up your data (BACKUP)" in the TR-1000 Owner's Manual.
- 1. Select the bell-shaped icon on the top right corner of the app.



2. Select "Download & Update".



The progress bar advances, and the following message is shown.



Next, operate the unit.

3. Use the [C6/VALUE] knob to select "OK", and press the [ENTER] button.




The progress bar advances, and once the message "Completed. Turn off power." appears, turn off the power.

Perform a factory reset after the update.

- * Refer to "Returning to the Factory Settings (FACTORY RESET)" (TR-1000 Owner's Manual) for details
- * The sound data and settings on the TR-1000 are lost once you execute the factory reset. Use the backup or export function to save any necessary data before you perform the factory reset.


Screen layout

Overview



INST

This screen is shown when INST is selected from the FUNCTION tabs. The parameters that are managed by the kit are shown. For details on each parameter, refer to the "TR-1000 Owner's Manual".



INST FX

This screen is shown when the INST FX tab is selected.




WRITE INST

This screen is shown when WRITE is selected for the instrument.



MIXER


This screen is shown when MIXER is selected from the FUNCTION tabs. The parameters that are managed by the kit and pattern are shown.



MIXER

INST BANK

This screen is shown when INST BANK is selected. Use this to call up instruments for the kit.



Select the number or instrument name to sort the list.

KIT

This screen is shown when KIT is selected from the FUNCTION tabs. The parameters that are managed by the kit are shown.



KIT SELECT

This screen is shown when KIT is selected. Shows the KIT list.



WRITE KIT

This screen is shown when WRITE is selected for the kit. This selects the write destination kit.



SAMPLE MEMORY

This screen is shown when Sample Memory is selected. This shows information regarding the sample capacity.



MODULATOR LFO (KIT)

This screen is shown when Mod (Kit) is selected.




SIDE CHAIN

This screen is shown when Side Chain is selected.



MENU

This screen is shown when the menu is selected.






IMPORT SAMPLE

This screen is shown when Import Sample is selected in the menu.



EXPORT SAMPLE

This screen is shown when Export Sample is selected in the menu.



TRANSFER BACKUP

This screen is shown when Transfer Backup is selected in the menu.



SYSTEM

This screen is shown when SYSTEM is selected.

